



Monitoring the RHEV Manager

eG Enterprise v6

Restricted Rights Legend

The information contained in this document is confidential and subject to change without notice. No part of this document may be reproduced or disclosed to others without the prior permission of eG Innovations, Inc. eG Innovations, Inc. makes no warranty of any kind with regard to the software and documentation, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose.

Trademarks

Microsoft Windows, Windows NT, Windows 2003, and Windows 2000 are either registered trademarks or trademarks of Microsoft Corporation in United States and/or other countries.

The names of actual companies and products mentioned herein may be the trademarks of their respective owners.

Copyright

© 2015 eG Innovations, Inc. All rights reserved.


The copyright in this document belongs to eG Innovations, Inc. Complying with all applicable copyright laws is the responsibility of the user.

Table of Contents

MONITORING THE RHEV MANAGER	2
1.1 The Application Processes Layer.....	4
1.1.1 RHEV Manager Log Test	4
1.2 The RHEV Infrastructure Layer.....	9
1.2.1 Storage Domains Test	9
1.2.2 RHEV Events Test	12
1.3 Virtual Machine Clusters	14
1.3.1 Clusters Test.....	14
1.4 The Datacenters Layer	17
1.4.1 RHEV Datacenters Test	17
1.4.2 RHEV Clusters Test.....	22
CONCLUSION	25

Table of Figures

Figure 1.1: The layer model of the RHEV Manager	3
Figure 1.2: The tests mapped to the Application Processes layer	4
Figure 1.3: The detailed diagnosis of the Recent messages measure	8
Figure 1.4: The tests mapped to the RHEV infrastructure	9
Figure 1.9: The test mapped to the Virtual Machine Clusters layer	14
Figure 1.10: The tests mapped to the Datacenters layer	17
Figure 1.11: The detailed diagnosis of the Clusters in datacenter measure	21
Figure 1.12: The detailed diagnosis of the RHEV servers in datacenter measure	22
Figure 1.13: The detailed diagnosis of the VMs in datacenter measure	22
Figure 1.14: The detailed diagnosis of the Storage domains in datacenter measure.....	22



Monitoring the RHEV Manager

Red Hat Enterprise Virtualization Manager delivers a centralized management system to administer and control all aspects of a virtualized infrastructure from host and guest management through to storage management and high availability. Red Hat Enterprise Virtualization (RHEV) manager provides a rich user interface that allows an administrator to manage their virtual infrastructure from a web browser allowing even the most advanced configurations such as network bonding and VLANs to be centrally managed from a graphical console. RHEV manager manages both Red Hat Enterprise Virtualization Hypervisors (RHEV-H) and Red Hat Enterprise Linux 5 hosts with the KVM hypervisor, delivering leading performance and scalability for virtual machines.

Using the RHEV manager, administrators can effortlessly relocate virtual machines to another host within a cluster and thus dynamically balance resources in a cluster. Moreover, with the help of the Image Manager on the RHEV manager, administrators can provision new virtual machines based on templates in no time.

However, this dependence on the RHEV manager may have its disadvantages. For instance, if the RHEV manager is unexpectedly rendered unavailable over the network, or when the event log captures a serious error on the manager but you have no knowledge of it, then your ability to manage the virtualized infrastructure may be crippled for brief or even prolonged time periods! The only way by which such adversities can be avoided is by continuously monitoring the availability and overall health of the RHEV manager and proactively detecting such deviations before end-users are affected.

eG Enterprise provides a 100%, web-based *RHEV Manager* monitoring model, which periodically runs availability and health checks on the RHEV manager and proactively reports abnormalities.




Figure 1.1: The layer model of the RHEV Manager

Each layer of Figure 1.1 is mapped to tests, which employ agent-based or agentless mechanisms (depending upon how you want the RHEV manager to be monitored by the eG Enterprise system) to pull out a variety of metrics from the RHEV manager. To enable the tests to collect the required metrics, you need to configure each test with the following:

- The domain to which the RHEV manager belongs
- The credentials of a user who has been assigned the **RHEVMUser** role

The metrics so collected enable administrators to quickly find accurate answers to the following performance queries:

- Is the RHEV manager available over the network? If so, how quickly is it responding to requests?
- Have any error/warning events occurred on the RHEV manager? What are these errors/warnings?
- Has the RHEV manager log captured any new errors/warnings? If so, what are they?
- How many data centers have been configured on the RHEV manager? What are they, and what is the compatibility level of each one of them?
- Is any data center in a problematic state currently?
- Which data center is running short of disk space? How many clusters, RHEV servers, and VMs have been configured in that data center, and which ones are they?
- How many storage domains are operational in each datacenter? Which ones are they?
- Is any storage domain unavailable? If so, which one? Which VMs are using this storage domain?
- Is any storage domain running out of space? Which one is it, and which VMs will be impacted by this space crunch?
- Is any logical network currently down? Which clusters and RHEV servers are using this logical network?
- Which logical network is experiencing heavy network traffic?
- Have any errors occurred on a logical network? If so, which one is it, and when did these errors occur - while transmitting data or while receiving it?
- Is any cluster using CPU resources excessively? If so, which cluster is it? Are any CPU-hungry VMs operating within that cluster? What are they?
- Are all clusters rightly sized in terms of memory, or are there any clusters that are currently experiencing a memory contention? If so, which cluster is it, and what is causing the memory crunch on that cluster - is it owing to improperly sized hosts or memory-starved VMs?

- Which cluster has too many hosts and VMs that are powered off?
- What is the compatibility level of each cluster?

As the bottom 3 layers of Figure 1.1 have already been dealt with in the *Monitoring Unix and Windows Servers* document, let us focus on the top 4 layers alone.

1.1 The Application Processes Layer

Besides monitoring the critical processes executing on the RHEV manager's host and reporting the resource usage of these processes, this layer also scans the RHEV manager log file that you specify for error/warning messages of specific patterns and promptly alerts administrators when a pattern match is found. Recent error/warning events are thus captured and reported.




Figure 1.2: The tests mapped to the Application Processes layer

1.1.1 RHEV Manager Log Test

This test periodically monitors the RHEV manager's log file for messages of configured patterns and promptly alerts users when messages that match these patterns are found in the log file. This way, the test captures and reports errors/warnings almost as soon as they occur.

Purpose	Periodically monitors the RHEV manager's log file for messages of configured patterns and promptly alerts users when messages that match these patterns are found in the log file
---------	---

Configurable parameters for the test	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured. 3. PORT – The port at which the server listens 4. ALERTFILE - Specify the path to the log file to be monitored. For eg., <code>/user/john/new_john.log</code>. Multiple log file paths can be provided as a comma-separated list - eg., <code>/user/john/critical_egurkha.log,/tmp/log/major.log</code>. <p>Also, instead of a specific log file path, the path to the directory containing log files can be provided - eg., <code>/user/logs</code>. This ensures that eG Enterprise monitors the most recent log files in the specified directory. Specific log file name patterns can also be specified. For example, to monitor the latest log files with names containing the strings 'dblogs' and 'applogs', the parameter specification can be, <code>/tmp/db/*dblogs*,/tmp/app/*applogs*</code>. Here, '*' indicates leading/trailing characters (as the case may be). In this case, the eG agent first enumerates all the log files in the specified path that match the given pattern, and then picks only the latest log file from the result set for monitoring.</p> <p>Your ALERTFILE specification can also be of the following format: <code>Name@filepath_or_pattern</code>. Here, <i>Name</i> represents the display name of the path being configured. Accordingly, the parameter specification for the 'dblogs' and 'applogs' example discussed above can be: <code>dblogs@/tmp/db/*dblogs*,applogs@/tmp/app/*applogs*</code>. In this case, the display names 'dblogs' and 'applogs' will alone be displayed as descriptors of this test.</p> <p>Every time this test is executed, the eG agent verifies the following:</p> <ol style="list-style-type: none"> c. Whether any changes have occurred in the size and/or timestamp of the log files that were monitoring during the last measurement period; d. Whether any new log files (that match the ALERTFILE specification) have been newly added since the last measurement period; <p>If a few lines have been added to a log file that was monitored previously, then the eG agent monitors the additions to that log file, and then proceeds to monitor newer log files (if any). If an older log file has been overwritten, then, the eG agent monitors this log file completely, and then proceeds to monitor the newer log files (if any).</p> <ol style="list-style-type: none"> 5. SEARCHPATTERN - Enter the specific patterns of alerts to be monitored. The pattern should be in the following format: <code><PatternName>:<Pattern></code>, where <code><PatternName></code> is the pattern name that will be displayed in the monitor interface and <code><Pattern></code> is an expression of the form - <code>*expr*</code> or <code>expr</code> or <code>*expr</code> or <code>expr*</code>, etc. A leading '*' signifies any number of leading characters, while a trailing '*' signifies any number of trailing characters. <p>For example, say you specify <code>ORA:ORA-*</code> in the SEARCHPATTERN text box. This indicates that "ORA" is the pattern name to be displayed in the monitor interface. "ORA-*" indicates that the test will monitor only those lines in the alert log which start with the term "ORA-". Similarly, if your pattern specification reads: <code>offline:*offline</code>, then it means that the pattern name is offline and that the test will monitor those lines in the alert log which end with the term offline.</p>
---	--

	<p>A single pattern may also be of the form e1+e2, where + signifies an OR condition. That is, the <PatternName> is matched if either e1 is true or e2 is true.</p> <p>Multiple search patterns can be specified as a comma-separated list. For example: ORA:ORA-*,offline:*offline*,online:*online</p> <p>If the ALERTFILE specification is of the format <i>Name@logfilepath</i>, then the descriptor for this test in the eG monitor interface will be of the format: <i>Name:PatternName</i>. On the other hand, if the ALERTFILE specification consists only of a comma-separated list of log file paths, then the descriptors will be of the format: <i>LogFilePath:PatternName</i>.</p> <p>If you want all the messages in a log file to be monitored, then your specification would be: <PatternName>:*</p> <p>6. LINES - Specify two numbers in the format x:y. This means that when a line in the alert file matches a particular pattern, then x lines before the matched line and y lines after the matched line will be reported in the detail diagnosis output (in addition to the matched line). The default value here is 0:0. Multiple entries can be provided as a comma-separated list.</p> <p>If you give 1:1 as the value for LINES, then this value will be applied to all the patterns specified in the SEARCHPATTERN field. If you give 0:0,1:1,2:1 as the value for LINES and if the corresponding value in the SEARCHPATTERN field is like ORA:ORA-*,offline:*offline*,online:*online then:</p> <p>0:0 will be applied to ORA:ORA-* pattern</p> <p>1:1 will be applied to offline:*offline* pattern</p> <p>2:1 will be applied to online:*online pattern</p> <p>7. EXCLUDEPATTERN - Provide a comma-separated list of patterns to be excluded from monitoring in the EXCLUDEPATTERN text box. For example *critical*, *exception*. By default, this parameter is set to 'none'.</p> <p>8. UNIQUEMATCH - By default, the UNIQUEMATCH parameter is set to FALSE, indicating that, by default, the test checks every line in the log file for the existence of each of the configured SEARCHPATTERNS. By setting this parameter to TRUE, you can instruct the test to ignore a line and move to the next as soon as a match for one of the configured patterns is found in that line. For example, assume that <i>Pattern1:*fatal*,Pattern2:*error*</i> is the SEARCHPATTERN that has been configured. If UNIQUEMATCH is set to FALSE, then the test will read every line in the log file completely to check for the existence of messages embedding the strings 'fatal' and 'error'. If both the patterns are detected in the same line, then the number of matches will be incremented by 2. On the other hand, if UNIQUEMATCH is set to TRUE, then the test will read a line only until a match for one of the configured patterns is found and not both. This means that even if the strings 'fatal' and 'error' follow one another in the same line, the test will consider only the first match and not the next. The match count in this case will therefore be incremented by only 1.</p>
--	--

9. **ROTATINGFILE** - This flag governs the display of descriptors for this test in the eG monitoring console.

If this flag is set to **true** and the **ALERTFILE** text box contains the full path to a specific (log/text) file, then, the descriptors of this test will be displayed in the following format: *Directory containing monitored file:<SearchPattern>*. For instance, if the **ALERTFILE** parameter is set to *c:\eGurkha\logs\syslog.txt*, and **ROTATINGFILE** is set to **true**, then, your descriptor will be of the following format: *c:\eGurkha\logs:<SearchPattern>*. On the other hand, if the **ROTATINGFILE** flag had been set to **false**, then the descriptors will be of the following format: *<FileName>:<SearchPattern>* - i.e., *syslog.txt:<SearchPattern>* in the case of the example above.

If this flag is set to **true** and the **ALERTFILE** parameter is set to the directory containing log files, then, the descriptors of this test will be displayed in the format: *Configured_directory_path:<SearchPattern>*. For instance, if the **ALERTFILE** parameter is set to *c:\eGurkha\logs*, and **ROTATINGFILE** is set to **true**, then, your descriptor will be: *c:\eGurkha\logs:<SearchPattern>*. On the other hand, if the **ROTATINGFILE** parameter had been set to **false**, then the descriptors will be of the following format: *Configured_directory:<SearchPattern>* - i.e., *logs:<SearchPattern>* in the case of the example above.

If this flag is set to **true** and the **ALERTFILE** parameter is set to a specific file pattern, then, the descriptors of this test will be of the following format: *<FilePattern>:<SearchPattern>*. For instance, if the **ALERTFILE** parameter is set to *c:\eGurkha\logs*sys**, and **ROTATINGFILE** is set to **true**, then, your descriptor will be: **sys*<SearchPattern>*. In this case, the descriptor format will not change even if the **ROTATINGFILE** flag status is changed.

10. **DD FREQUENCY** - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is 1:1. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying none against dd frequency.

11. **CASESENSITIVE** - This flag is set to **No** by default. This indicates that the test functions in a 'case-insensitive' manner by default. This implies that, by default, the test ignores the case of your **ALERTFILE** and **SEARCHPATTERN** specifications. If this flag is set to **Yes** on the other hand, then the test will function in a 'case-sensitive' manner. In this case therefore, for the test to work, even the case of your **ALERTFILE** and **SEARCHPATTERN** specifications should match with the actuals.

	<p>12. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option.</p> <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> ➤ The eG manager license should allow the detailed diagnosis capability ➤ Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 						
Outputs of the test	One set of results for every ALERTFILE and SEARCHPATTERN combination						
Measurements made by the test	<table border="1"> <thead> <tr> <th>Measurement</th> <th>Measurement Unit</th> <th>Interpretation</th> </tr> </thead> <tbody> <tr> <td>Recent messages: Indicates the number of messages of the configured SEARCHPATTERN that were logged in the specified log file since the last measurement period.</td> <td>Number</td> <td>The value of this measure is a clear indicator of the number of "new" alerts that have come into the alert log of the monitored RHEV manager. The detailed diagnosis of this measure, if enabled, provides the detailed descriptions of the errors of the configured patterns.</td> </tr> </tbody> </table>	Measurement	Measurement Unit	Interpretation	Recent messages: Indicates the number of messages of the configured SEARCHPATTERN that were logged in the specified log file since the last measurement period.	Number	The value of this measure is a clear indicator of the number of "new" alerts that have come into the alert log of the monitored RHEV manager. The detailed diagnosis of this measure, if enabled, provides the detailed descriptions of the errors of the configured patterns.
Measurement	Measurement Unit	Interpretation					
Recent messages: Indicates the number of messages of the configured SEARCHPATTERN that were logged in the specified log file since the last measurement period.	Number	The value of this measure is a clear indicator of the number of "new" alerts that have come into the alert log of the monitored RHEV manager. The detailed diagnosis of this measure, if enabled, provides the detailed descriptions of the errors of the configured patterns.					

Use the detailed diagnosis of the *Recent messages* measure to know the complete details of the messages of the configured **SEARCHPATTERN**. This serves as an effective troubleshooting tool.

Lists recent messages in the log file	
TIME	MESSAGES
Jan 09, 2012 16:30:03	
	2012-01-10 00:26:00,878 ERROR [org.nogah.vdsbroker.vdsbroker.VdsBrokerCommand] (QuartzScheduler_Worker-22) XML RPC error in command GetCapabilitiesVDS, the error was: java.util.concurrent.ExecutionException: java.lang.reflect.InvocationTargetException
	2012-01-10 00:26:05,923 ERROR [org.nogah.vdsbroker.vdsbroker.VdsBrokerCommand] (QuartzScheduler_Worker-34) XML RPC error in command GetCapabilitiesVDS, the error was: java.util.concurrent.ExecutionException: java.lang.reflect.InvocationTargetException
	2012-01-10 00:26:08,924 ERROR [org.nogah.vdsbroker.vdsbroker.VdsBrokerCommand] (QuartzScheduler_Worker-34) XML RPC error in command GetCapabilitiesVDS, the error was: java.util.concurrent.ExecutionException: java.lang.reflect.InvocationTargetException
	2012-01-10 00:26:13,957 ERROR [org.nogah.vdsbroker.vdsbroker.VdsBrokerCommand] (QuartzScheduler_Worker-40) XML RPC error in command GetCapabilitiesVDS, the error was: java.util.concurrent.ExecutionException: java.lang.reflect.InvocationTargetException
	2012-01-10 00:26:16,974 ERROR [org.nogah.vdsbroker.vdsbroker.VdsBrokerCommand] (QuartzScheduler_Worker-22) XML RPC error in command GetCapabilitiesVDS, the error was: java.util.concurrent.ExecutionException: java.lang.reflect.InvocationTargetException
	2012-01-10 00:26:21,015 ERROR [org.nogah.vdsbroker.vdsbroker.VdsBrokerCommand] (QuartzScheduler_Worker-22) XML RPC error in command GetCapabilitiesVDS, the error was: java.util.concurrent.ExecutionException: java.lang.reflect.InvocationTargetException
	2012-01-10 00:26:25,016 ERROR [org.nogah.vdsbroker.vdsbroker.VdsBrokerCommand] (QuartzScheduler_Worker-18) XML RPC error in command GetCapabilitiesVDS, the error was: java.util.concurrent.ExecutionException: java.lang.reflect.InvocationTargetException

Figure 1.3: The detailed diagnosis of the Recent messages measure

1.2 The RHEV Infrastructure Layer

The tests mapped to this layer focus on the current status and usage of the core components of an RHEV infrastructure, namely - the storage domains and the logical networks. In addition, the layer also provides you with periodic updates on error/warning events captured on the RHEV manager.




Figure 1.4: The tests mapped to the RHEV infrastructure

1.2.1 Storage Domains Test

A data center relies on adequate and accessible physical storage. The storage pool is a logical entity that contains a standalone image repository of a certain type, either iSCSI, or Fiber Channel, or NFS. Each Storage Pool may contain several storage domains, for Guests images, for ISO images and for Import/Export images.

If a storage domain becomes unavailable or runs out of space, then this will affect the operations of the VMs using that storage domain. To promptly detect the unavailability or abnormal usage of a storage domain and isolate the VMs that may be impacted by this, use the **Storage Domains** test.

Purpose	Promptly detects the unavailability or abnormal usage of a storage domain and helps isolate the VMs that may be impacted by this
----------------	--

Configurable parameters for the test	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT - The port at which the specified HOST listens. The default port is 8443. 4. RHEL MGR USER and RHEL MGR PASSWORD - To pull out the desired metrics from the RHEV manager, this test has to be configured with the privileges of a user who has been assigned the RHEVMIUser role. Specify the user name and password of this user in the RHEL MGR USER and RHEL MGR PASSWORD text boxes, respectively. 5. CONFIRM PASSWORD - Confirm the RHEL MGR PASSWORD by retyping it here. 6. RHEL MANAGER DOMAIN - Specify the domain to which the RHEV manager belongs. By default, <i>internal</i> is displayed here. 7. SSL - If the RHEV manager to which the eG agent should connect is SSL-enabled, then set this flag to Yes. If not, set it to No. 8. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 			
Outputs of the test	One set of results for each storage domain in each datacenter configured on the RHEV manager being monitored			
Measurements made by the test	<table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 33.33%;">Measurement</th> <th style="width: 33.33%;">Measurement Unit</th> <th style="width: 33.33%;">Interpretation</th> </tr> </thead> </table>	Measurement	Measurement Unit	Interpretation
Measurement	Measurement Unit	Interpretation		

	<p>Is master storage domain?:</p> <p>Indicates whether/not this storage domain is the master storage domain in this data center.</p>		<p>This measure will report the value <i>Yes</i> if the storage domain is the master, and <i>No</i> if it is the slave.</p> <p>The numeric values that correspond to the Yes/No values above are as follows:</p> <table border="1"> <thead> <tr> <th>Measure Value</th><th>Numeric Value</th></tr> </thead> <tbody> <tr> <td>Yes</td><td>1</td></tr> <tr> <td>No</td><td>0</td></tr> </tbody> </table> <p>Note:</p> <p>By default, this measure reports one of the Measure Values listed in the table above. The graph of this measure however will represent the storage domain type (master/slave) using the numeric equivalents - '0' or '1'.</p>	Measure Value	Numeric Value	Yes	1	No	0
Measure Value	Numeric Value								
Yes	1								
No	0								
	<p>Storage domain capacity:</p> <p>Indicates the current capacity of this storage domain.</p>	GB							
	<p>Used space:</p> <p>Indicates the amount of storage space currently utilized by this domain.</p>	GB	Ideally, the value of this measure should be low.						
	<p>Free space:</p> <p>Indicates the amount of storage space that is currently available for use in this storage domain.</p>	GB	Ideally, the value of this measure should be high.						
	<p>Committed space:</p> <p>Indicates the amount of storage space currently committed in this storage domain.</p>	GB							
	<p>Storage domain space usage:</p> <p>Indicates the percentage of total storage space in this storage domain that is currently being utilized.</p>	Percent	<p>Compare the value of this measure across domains to identify the domain that is experiencing a space drain.</p> <p>A high value or a consistent increase in this value is a cause for concern, as it indicates the steady erosion of storage space from a storage domain. If a storage domain runs out of space, it will affect the operations of all VMs that use that domain.</p>						

	Storage domain in datacenter: Indicates whether/not this storage domain is currently available in the datacenter.	Percent	While the value 0 indicates that the storage domain is unavailable, the value 100 indicates that the storage domain is currently available. If a storage domain used by a VM is rendered unavailable, users will be denied access to that VM.
--	---	---------	--

1.2.2 RHEV Events Test

This test enables administrators to promptly capture and report the count and details of critical information, error, and warning events that are generated on the RHEV manager.

By default, the test monitors a pre-defined set of events belonging to pre-configured event categories. You can override this default setting by including/excluding specific events from an event category or by adding more categories. To achieve this, do the following:

- Edit the `eg_tests.ini` file in the `<EG_INSTALL_DIR>\manager\config` directory.
- In the **[RhevEvents]** section of this file, you will find the event categories that are currently monitored by **RHEV Events** test, and the individual events of each category. The format of these entries is:
RHEVEventsTest:<EventCategory>=<Comma-separated list of eventsIDs grouped under this category>
- To add a new event category to the list, you just need to append a line to the **[RhevEvents]** section in the format mentioned above. For instance, say, you want to include a category named **ImportExportEvents** to event categories that pre-exist. In this case, you will have to insert a line in the **[RhevEvents]** section for this category, as mentioned below:
RHEVEventsTest:ImportExportEvents=1150,1151,1152,1153
- Finally, save the file.

Purpose	Promptly capture and report the count and details of critical information, error, and warning events that are generated on the RHEV manager
----------------	---

Configurable parameters for the test	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT - The port at which the specified HOST listens. The default port is 8443. 4. RHEL MGR USER and RHEL MGR PASSWORD - To pull out the desired metrics from the RHEV manager, this test has to be configured with the privileges of a user who has been assigned the RHEVMIUser role. Specify the user name and password of this user in the RHEL MGR USER and RHEL MGR PASSWORD text boxes, respectively. 5. CONFIRM PASSWORD - Confirm the RHEL MGR PASSWORD by retyping it here. 6. RHEL MANAGER DOMAIN - Specify the domain to which the RHEV manager belongs. By default, <i>internal</i> is displayed here. 7. SSL - If the RHEV manager to which the eG agent should connect is SSL-enabled, then set this flag to Yes. If not, set it to No. 8. DD FREQUENCY - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is 1:1. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying none against dd frequency. 9. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 						
Outputs of the test	One set of results for each event category pre-defined in the eg_tests.ini file (in the <EG_INSTALL_DIR>\manager\config directory)						
Measurements made by the test	<table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="text-align: center; width: 33.33%;">Measurement</th><th style="text-align: center; width: 33.33%;">Measurement Unit</th><th style="text-align: center; width: 33.33%;">Interpretation</th></tr> </thead> <tbody> <tr> <td style="vertical-align: top;"> Total events: Indicates the total number of events that occurred on the RHEV manager since the last measurement period. </td><td style="text-align: center; vertical-align: top;"> Number </td><td></td></tr> </tbody> </table>	Measurement	Measurement Unit	Interpretation	Total events: Indicates the total number of events that occurred on the RHEV manager since the last measurement period.	Number	
Measurement	Measurement Unit	Interpretation					
Total events: Indicates the total number of events that occurred on the RHEV manager since the last measurement period.	Number						
	<table border="1" style="width: 100%; border-collapse: collapse;"> <tbody> <tr> <td style="vertical-align: top;"> Information: Indicates the number of general information events that occurred on the RHEV manager since the last measurement period. </td><td style="text-align: center; vertical-align: top;"> Number </td><td></td></tr> </tbody> </table>	Information: Indicates the number of general information events that occurred on the RHEV manager since the last measurement period.	Number				
Information: Indicates the number of general information events that occurred on the RHEV manager since the last measurement period.	Number						

	Errors: Indicates the number of error events that were captured on the RHEV manager since the last measurement period.	Number	Ideally, the value of this measure should be 0. A high value is a cause for concern. Use the detailed diagnosis of this measure to know what the errors are, so that you can troubleshoot the issues efficiently.
	Warnings: Indicates the number of warning events that were captured on the RHEV manager since the last measurement period.	Number	Ideally, the value of this measure should be 0. A high value is a cause for concern. Use the detailed diagnosis of this measure to know what the warnings are, so that potential anomalies can be identified early and resolved quickly.

1.3 Virtual Machine Clusters

A cluster is a set of physical hosts that are treated as a resource pool for a set of virtual machines. Hosts in a cluster share the same network infrastructure and the same storage. They are a migration domain within which virtual machines can be moved from host to host.

Using the test mapped to this layer, you can quickly understand how much CPU/memory/storage resources are available with each cluster managed by an RHEV manager, and assess how well every cluster utilizes the available resources. In the process, the test points you to those clusters that may run the risk of a resource contention in the future.




Figure 1.5: The test mapped to the Virtual Machine Clusters layer

1.3.1 Clusters Test

This test reports key metrics pertaining to the resource availability and resource usage of the RHEV server clusters managed by the RHEV manager.

Purpose	Reports key metrics pertaining to the resource availability and resource usage of the RHEV
---------	--

	server clusters managed by the RHEV manager		
Configurable parameters for the test	<ol style="list-style-type: none"> TEST PERIOD - How often should the test be executed HOST - The host for which the test is to be configured PORT - The port at which the specified HOST listens. The default port is 8443. RHEL MGR USER and RHEL MGR PASSWORD - To pull out the desired metrics from the RHEV manager, this test has to be configured with the privileges of a user who has been assigned the RHEVMIUser role. Specify the user name and password of this user in the RHEL MGR USER and RHEL MGR PASSWORD text boxes, respectively. CONFIRM PASSWORD - Confirm the RHEL MGR PASSWORD by retyping it here. RHEL MANAGER DOMAIN - Specify the domain to which the RHEV manager belongs. By default, <i>internal</i> is displayed here. SSL - If the RHEV manager to which the eG agent should connect is SSL-enabled, then set this flag to Yes. If not, set it to No. DD FREQUENCY - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is 1:1. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying none against dd frequency. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> The eG manager license should allow the detailed diagnosis capability Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 		
Outputs of the test	One set of results for each cluster in each datacenter configured on the RHEV manager being monitored		
Measurements made by the test	Measurement	Measurement Unit	Interpretation

	VMs powered on: Indicates the number of VMs that are currently powered on in this cluster.	Number							
	VMs powered off: Indicates the number of VMs that are currently powered off in this cluster.	Number	Use the detailed diagnosis of this measure to identify the powered off VMs in a cluster.						
	VMs suspended: Indicates the number of VMs in this cluster that are currently in a suspended state .	Number							
	Other VMs: Indicates the number of VMs in this cluster that are in an UNKNOWN state, are not responding, and are unassigned.	Number	Use the detailed diagnosis of this measure to know which VMs are in an UNKNOWN state, are not responding, and are unassigned.						
	Max memory over commitment: Indicates the maximum percentage of memory this cluster is configured to over-commit.	Percent	Memory overcommitment, when configured at the cluster-level, allows the allocation of more virtual memory to the VMs in a cluster than the physical memory available to the hosts in the cluster.						
	Use thread as CPU: Indicates whether this cluster has been configured to treat host CPU threads as cores.		<p>Clusters can be configured to treat CPU threads as cores for the purposes of virtual machine resource allocation and migration.</p> <p>The values this measure can report and their corresponding numeric values are listed below:</p> <table border="1"> <thead> <tr> <th>Measure Value</th> <th>Numeric Value</th> </tr> </thead> <tbody> <tr> <td>Yes</td> <td>1</td> </tr> <tr> <td>No</td> <td>0</td> </tr> </tbody> </table> <p>By default, this measure reports the Measure Values listed in the table above to report the status of the 'Use thread as CPU' flag. In the graph of this measure however, this status is indicated using the numeric equivalents only.</p>	Measure Value	Numeric Value	Yes	1	No	0
Measure Value	Numeric Value								
Yes	1								
No	0								

	Total hosts: Indicates the total number of hosts in this cluster.	Number	
--	---	--------	--

1.4 The Datacenters Layer

A data center is a logical entity that defines the set of resources used in a specific environment. It is a collection of a number of clusters of virtual machines, storage and networks. The data center is the highest level container for all physical and logical resources within a managed virtual environment.

Using the test associated with this layer, you can determine the following:

- The number and names of storage domains, clusters, RHEV servers, and VMs that are managed by every data center on the RHEV manager;
- The disk space resources available to each datacenter, and how well every data center utilizes the space resources - this way, the test accurately points you to data centers that are starved of disk space.



Figure 1.6: The tests mapped to the Datacenters layer

1.4.1 RHEV Datacenters Test

This test auto-discovers the data centers configured on an RHEV manager and reports the composition, resource availability, and resource usage of each data center. This way, the test turns the spot light on those data centers that are headed towards a potential resource contention.

Purpose	Auto-discovers the data centers configured on an RHEV manager and reports the composition, resource availability, and resource usage of each data center
----------------	--

Configurable parameters for the test	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT - The port at which the specified HOST listens. The default port is 8443. 4. RHEL MGR USER and RHEL MGR PASSWORD - To pull out the desired metrics from the RHEV manager, this test has to be configured with the privileges of a user who has been assigned the RHEVMIUser role. Specify the user name and password of this user in the RHEL MGR USER and RHEL MGR PASSWORD text boxes, respectively. 5. CONFIRM PASSWORD - Confirm the RHEL MGR PASSWORD by retyping it here. 6. RHEL MANAGER DOMAIN - Specify the domain to which the RHEV manager belongs. By default, <i>internal</i> is displayed here. 7. SSL - If the RHEV manager to which the eG agent should connect is SSL-enabled, then set this flag to Yes. If not, set it to No. 8. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 			
Outputs of the test	One set of results for every data center configured on the RHEV manager being monitored			
Measurements made by the	<table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 33.33%;">Measurement</th> <th style="width: 33.33%;">Measurement Unit</th> <th style="width: 33.33%;">Interpretation</th> </tr> </thead> </table>	Measurement	Measurement Unit	Interpretation
Measurement	Measurement Unit	Interpretation		

test	<p>Datacenter status</p> <p>Indicates the current status of this data center.</p>		<p>The values that this measure can report and their numeric equivalents have been detailed in the table below:</p> <table border="1" data-bbox="984 302 1432 650"> <thead> <tr> <th data-bbox="984 302 1188 354">Measure Value</th><th data-bbox="1188 302 1432 354">Numeric Value</th></tr> </thead> <tbody> <tr> <td data-bbox="984 354 1188 407">Not operational</td><td data-bbox="1188 354 1432 407">0</td></tr> <tr> <td data-bbox="984 407 1188 460">Up</td><td data-bbox="1188 407 1432 460">1</td></tr> <tr> <td data-bbox="984 460 1188 513">Uninitialized</td><td data-bbox="1188 460 1432 513">2</td></tr> <tr> <td data-bbox="984 513 1188 566">Maintenance</td><td data-bbox="1188 513 1432 566">3</td></tr> <tr> <td data-bbox="984 566 1188 618">Problematic</td><td data-bbox="1188 566 1432 618">4</td></tr> <tr> <td data-bbox="984 618 1188 671">Contend</td><td data-bbox="1188 618 1432 671">5</td></tr> </tbody> </table> <p>Note:</p> <p>By default, this measure reports one of the Measure Values listed in the table above. The graph of this measure however will represent status using the numeric equivalents - '0' or '1'.</p>	Measure Value	Numeric Value	Not operational	0	Up	1	Uninitialized	2	Maintenance	3	Problematic	4	Contend	5
Measure Value	Numeric Value																
Not operational	0																
Up	1																
Uninitialized	2																
Maintenance	3																
Problematic	4																
Contend	5																
	<p>Storage domains in data center:</p> <p>Indicates the current number of storage domains in the data center.</p>	Number	Use the detailed diagnosis of this measure to know which storage domains are part of the data center.														
	<p>Datacenter disk capacity:</p> <p>Indicates the total disk capacity of this data center.</p>	GB															
	<p>Free space in datacenter:</p> <p>Indicates the total unused space in this datacenter.</p>	GB	A high value is desired for this measure.														
	<p>Used space in datacenter:</p> <p>Indicates the amount of disk space that is currently utilized in this data center.</p>	GB	Ideally, the value of this measure should be low.														

	Percentage of free space in datacenter: Indicates the percentage of disk space that is currently free in this data center.	Percent	A low value or a steady decrease in the value of this measure indicates the gradual erosion of disk space from the hosts in the data center. If the situation persists, then the data center may suddenly run very low on disk space, causing the hosts and VMs in the data center to fight over the meager resources. This in turn will affect the performance of the VMs, hosts, and the applications executing on the VMs.
	Clusters in datacenter: Indicates the current number of clusters in this data center.	Number	Use the detailed diagnosis of this measure to know which clusters are part of the data center.
	RHEV servers in datacenter: Indicates the current number of RHEV servers in this data center.	Number	Use the detailed diagnosis of this measure to know which RHEV servers are part of the data center.
	VMs in datacenter: Indicates the current number of VMs in this data center.	Number	Use the detailed diagnosis of this measure to know which virtual machines are part of the data center.

	Compatibility version: Indicates the compatibility level of this data center.	Number	Each host connected to Red Hat Enterprise Virtualization Manager contains a version of VDSM. VDSM is the agent within the virtualization infrastructure that runs on a hypervisor or host and provides local management for virtual machines, networks and storage. Red Hat Enterprise Virtualization Manager controls hypervisors and hosts using current or older versions of VDSM. The Manager migrates virtual machines from host to host within a cluster. This means the Manager excludes certain features from a current version of VDSM until all hosts within a cluster have the same VDSM version, or more recent, installed.
	Supported version: Indicates the supported version of this data center.	Number	The API represents this concept as a compatibility level for each host, corresponding to the version of VDSM installed. A version element contains major and minor attributes, which describe the compatibility level. When an administrator upgrades all hosts within a cluster to a certain level, the version level appears under a supported_versions element. This indicates the cluster's version is now updatable to that level. Once the administrator updates all clusters within a data center to a given level, the data center is updatable to that level.

The detailed diagnosis of the *Clusters in datacenter* reports the names of the clusters that are part of a particular data center.

Shows the name of the clusters in datacenter	
TIME	CLUSTER NAME
Jan 09, 2012 16:44:24	Default

Figure 1.7: The detailed diagnosis of the Clusters in datacenter measure

The detailed diagnosis of the *RHEV servers in datacenter* reports the names and IP addresses of the RHEV servers that are part of a particular data center.

MONITORING THE RHEV MANAGER

Detailed Diagnosis Measure Graph Summary Graph Trend Graph Fix History Fix Feedback

Component: 192.168.8.8:8443 Measured By: 192.168.8.192
 Test: Datacenters
 Description: Default Measurement: RHEV servers in datacenter
 Timeline: 1 hour From: Jan 09, 2012 Hr: 15 Min: 46 To: Jan 09, 2012 Hr: 16 Min: 46 Submit CSV

Shows the details of RHEV servers in datacenter

TIME	HOST NAME	HOST IP
Jan 09, 2012 16:44:24	rhevbasehyp6.mas.eginnovations.com	192.168.8.89

Figure 1.8: The detailed diagnosis of the RHEV servers in datacenter measure

The detailed diagnosis of the *VMs in datacenter* measure reports the names and IP addresses of the VMs that are part of a particular data center.

Detailed Diagnosis Measure Graph Summary Graph Trend Graph Fix History Fix Feedback

Component: 192.168.8.8:8443 Measured By: 192.168.8.192
 Test: Datacenters
 Description: Default Measurement: VMs in datacenter
 Timeline: 1 hour From: Jan 09, 2012 Hr: 15 Min: 48 To: Jan 09, 2012 Hr: 16 Min: 48 Submit CSV

Shows the details of virtual machines in datacenter

TIME	VM NAME	HOST NAME	HOST IP
Jan 09, 2012 16:44:24	FreePool-1	N/A	N/A
	NewRhel5X64	rhevbasehyp6.mas.eginnovations.com	192.168.8.89
	NX_XP1	rhevbasehyp6.mas.eginnovations.com	192.168.8.89
	RHEL54x64	rhevbasehyp6.mas.eginnovations.com	192.168.8.89
	XPSP3_testing	N/A	192.168.8.89

Figure 1.9: The detailed diagnosis of the VMs in datacenter measure

The detailed diagnosis of the *Storage domains in datacenter* measure reports the name and type of each storage domain that is part of a particular data center.

Detailed Diagnosis Measure Graph Summary Graph Trend Graph Fix History Fix Feedback

Component: 192.168.8.8:8443 Measured By: 192.168.8.192
 Test: Datacenters
 Description: Default Measurement: Storage domains in datacenter
 Timeline: 1 hour From: Jan 09, 2012 Hr: 15 Min: 45 To: Jan 09, 2012 Hr: 16 Min: 45 Submit CSV

Shows the details of storage domains in datacenter

TIME	STORAGE DOMAIN NAME	STORAGE DOMAIN TYPE
Jan 09, 2012 16:44:24	ISO_DOMAIN	iso
	DATA_STORE	data

Figure 1.10: The detailed diagnosis of the Storage domains in datacenter measure

1.4.2 RHEV Clusters Test

This test auto-discovers the data centers configured on an RHEV manager and reports the composition, resource availability, and resource usage of each data center. This way, the test turns the spot light on those data centers that are headed towards a potential resource contention.

Purpose	Auto-discovers the data centers configured on an RHEV manager and reports the composition, resource availability, and resource usage of each data center
---------	--

Configurable parameters for the test	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT - The port at which the specified HOST listens. The default port is 8443. 4. RHEL MGR USER and RHEL MGR PASSWORD - To pull out the desired metrics from the RHEV manager, this test has to be configured with the privileges of a user who has been assigned the RHEVMIUser role. Specify the user name and password of this user in the RHEL MGR USER and RHEL MGR PASSWORD text boxes, respectively. 5. CONFIRM PASSWORD - Confirm the RHEL MGR PASSWORD by retyping it here. 6. RHEL MANAGER DOMAIN - Specify the domain to which the RHEV manager belongs. By default, <i>internal</i> is displayed here. 7. SSL - If the RHEV manager to which the eG agent should connect is SSL-enabled, then set this flag to Yes. If not, set it to No. 8. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 		
Outputs of the test	One set of results for every data center configured on the RHEV manager being monitored		
Measurements made by the	Measurement	Measurement Unit	Interpretation

test	<p>Datacenter status</p> <p>Indicates the current status of this data center.</p>		<p>The values that this measure can report and their numeric equivalents have been detailed in the table below:</p> <table border="1" data-bbox="992 302 1432 650"> <thead> <tr> <th data-bbox="1000 312 1188 354">Measure Value</th><th data-bbox="1188 312 1424 354">Numeric Value</th></tr> </thead> <tbody> <tr> <td data-bbox="1000 365 1188 407">Not operational</td><td data-bbox="1188 365 1424 407">0</td></tr> <tr> <td data-bbox="1000 418 1188 460">Up</td><td data-bbox="1188 418 1424 460">1</td></tr> <tr> <td data-bbox="1000 470 1188 513">Uninitialized</td><td data-bbox="1188 470 1424 513">2</td></tr> <tr> <td data-bbox="1000 523 1188 566">Maintenance</td><td data-bbox="1188 523 1424 566">3</td></tr> <tr> <td data-bbox="1000 576 1188 618">Problematic</td><td data-bbox="1188 576 1424 618">4</td></tr> <tr> <td data-bbox="1000 629 1188 671">Contend</td><td data-bbox="1188 629 1424 671">5</td></tr> </tbody> </table> <p>Note:</p> <p>By default, this measure reports one of the Measure Values listed in the table above. The graph of this measure however will represent status using the numeric equivalents - '0' or '1'.</p>	Measure Value	Numeric Value	Not operational	0	Up	1	Uninitialized	2	Maintenance	3	Problematic	4	Contend	5
Measure Value	Numeric Value																
Not operational	0																
Up	1																
Uninitialized	2																
Maintenance	3																
Problematic	4																
Contend	5																

Chapter

2

Conclusion

This document has described in detail the monitoring paradigm used and the measurement capabilities of the eG Enterprise suite of products with respect to **RHEV**. For details of how to administer and use the eG Enterprise suite of products, refer to the user manuals.

We will be adding new measurement capabilities into the future versions of the eG Enterprise suite. If you can identify new capabilities that you would like us to incorporate in the eG Enterprise suite of products, please contact support@eginnovations.com. We look forward to your support and cooperation. Any feedback regarding this manual or any other aspects of the eG Enterprise suite can be forwarded to feedback@eginnovations.com.